


PuTTY

Just enter the IP address of your receiver into the Host Name box and set the connection type and port as below.

You can get your IP address from **MENU > INFORMATION > NETWORK** or by logging into your router.

If you want to save your settings just enter the name of your receiver in the box under Saved Sessions and click the save button.



Press the open button and a terminal window will open.

Enter **root** (all lower case) and press enter.

If it then requests a password, enter the password that has been set on the receiver and press enter.



Copy the script from the Willobuild homepage and right click in the terminal window to paste.

Press enter and the script will start the flashing process.

Follow the onscreen instructions to flash the correct image for your receiver.

ENTERING A PASSWORD WITH PUTTY

Willo3092
June 2021



TYPE root AND PRESS ENTER



A screenshot of a PuTTY terminal window titled "192.168.0.222 - PuTTY". The terminal displays the following text: "Welcome to OpenViX for sf8008", "openvix 5.4 sf8008", "sf8008 login: root", "Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0", and "root@sf8008:~#". A green cursor is visible at the end of the prompt.

```
Welcome to OpenViX for sf8008
openvix 5.4 sf8008

sf8008 login: root
Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0
root@sf8008:~#
```

TYPE `passwd` AND PRESS ENTER

THE SCREEN WILL REMAIN INACTIVE WHILST ENTERING PASSWORDS




A screenshot of a PuTTY terminal window titled "192.168.0.222 - PuTTY". The terminal displays the same text as the previous screenshot, but with the addition of "root@sf8008:~# passwd" and "New password:". A green cursor is visible at the end of the "New password:" prompt.

```
Welcome to OpenViX for sf8008
openvix 5.4 sf8008

sf8008 login: root
Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0
root@sf8008:~# passwd
New password:
```

TYPE A 4 DIGIT NUMBER OR LETTERS AND PRESS ENTER

RETYPE THE 4 DIGIT NUMBER OR LETTERS AND PRESS ENTER



A screenshot of a PuTTY terminal window titled "192.168.0.222 - PuTTY". The terminal displays the following text: "Welcome to OpenViX for sf8008", "openvix 5.4 sf8008", "sf8008 login: root", "Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0", "root@sf8008:~# passwd", "New password:", and "Retype new password:". A green cursor is visible at the end of the "Retype new password:" line.

```
Welcome to OpenViX for sf8008
openvix 5.4 sf8008

sf8008 login: root
Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0
root@sf8008:~# passwd
New password:
Retype new password: █
```



A screenshot of a PuTTY terminal window titled "192.168.0.222 - PuTTY". The terminal displays the following text: "Welcome to OpenViX for sf8008", "openvix 5.4 sf8008", "sf8008 login: root", "Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0", "root@sf8008:~# passwd", "New password:", "Retype new password:", "passwd: password updated successfully", and "root@sf8008:~#". A green cursor is visible at the end of the "root@sf8008:~#" line.

```
Welcome to OpenViX for sf8008
openvix 5.4 sf8008

sf8008 login: root
Last login: Sun Jan 31 17:56:21 GMT 2021 on pts/0
root@sf8008:~# passwd
New password:
Retype new password:
passwd: password updated successfully
root@sf8008:~# █
```